

PocketSphinx (and Flite)

- **Web site** : <http://cmusphinx.sourceforge.net>

PocketSphinx is one of Carnegie Mellon University's open source large vocabulary, speaker-independent continuous speech recognition engine.

List of requested packages:

- Sphinx Base V0.4.99 : sphinxbase-0.4.99-latest.tar.gz → 5prealpha
- Pocket Sphinx : pocketsphinx-0.5.99-latest.tar.gz → 5prealpha
- uniMRCP V1.3.0 : unimrcp-1.3.0.tar.gz
- uniMRCP deps V1.3.0 : unimrcp-deps-1.3.0.tar.gz
- Asterisk 11 : asterisk-11-current.tar.gz
- Asterisk uniMRCP V1.3.1 : asterisk-unimrcp-1.3.1.tar.gz
- Flite V2.0.0 : flite-2.0.0-release.tar

Build the uniMRCP with PocketSphinx and Flite:

Follow the uniMRCP documented steps : <https://code.google.com/p/unimrcp/wiki/PocketSphinxPlugin>

- On Debian add: python, python-dev, swig.
- Compile SphinxBase (configure + make)
- Compile PocketSphinx (configure + make)
- Compile Flite (configure CFLAGS="-fPIC" + make)
- Compile unimrcp-deps if not already done (script build-dep-libs.sh)
- Patch the uniMRCP with the files (in patches/asterisk-unimrcp CVS module)
 - unimrcp/configure.ac
 - unimrcp/plugins/Makefile.am
 - unimrcp/plugins/mrcp-pocketsphinx (directory)
 - unimrcp/plugins/mrcp-pocketsphinx (directory)
 - unimrcp/build/acmacros/*.m4
- Change directory to unimrcp, and execute the bootstrap
- Compile mrcp-pocketsphinx with :
 - ./configure --enable-pocketsphinx-plugin --with-pocketsphinx=/datas/voicebrowser/pocketsphinx-5prealpha --with-sphinxbase=/datas/voicebrowser/sphinxbase-5prealpha
- Compile mrcp-flite with :
 - ./configure --enable-flite-plugin --with-flite=/datas/voicebrowser/flite-2.0.0-release CFLAGS="-fPIC"

Installation and configuration:

Over the uniMRCP standard installation, create those directories if necessary in /usr/local/unimrcp

- /bin : copy the binaries unimrcpsvr and unimrcpclnt from unimrcp-x.x.x/platforms/*.
- /plugin : copy the libraries generated from unimrcp-x.x.x/plugins/*.libs/* to this directory.
- /conf : add the pocketsphinx.xml from mrcp-pocketsphinx/conf and unimrcpsvr.xml configuration files (from patches/asterisk-unimrcp CVS module).
- /var : create only.
- /data : Copy the models and the dictionaies.

From:

<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:

<https://wiki.voximal.com/doku.php?id=community:pocketsphinx&rev=1447753714>

Last update: **2015/11/17 09:48**

