

Nuance ASR

About

Nuance

Nuance Communications, Inc.

Worldwide Headquarters

1 Wayside Road

Burlington, MA 01803

USA

Website: <http://www.nuance.com>

Definition

Nuance Recognizer is built on the 10th-generation of our ASR engine and delivers the industry's highest recognition accuracy, increasing the efficiency of self-service solutions. It easily understands and interprets spoken and touchtone input to help you deliver seamless self-service and an enhanced customer experience.

Languages

Arabic · Czech · Danish · Dutch (BE, NL) · English (UK, US) · Finnish , French(FR, Canadian) · German · Greek, Italian · Norwegian · Polish · Portuguese (PT, Brazil) · Russian · Spanish (Castillan ES) · Spanish (North America) · Spanish (Catalan) · Spanish (Galician) · Swedish · Turkish · Chinese

Installation

Log on your Linux machine as root.

Disable any Security Level enforcement (Firewall and SELinux).

Install the License Manager

With Centos 6 64bit, you need to install the redhat-lsb library by running this command :

```
#yum -y install redhat-lsb
```

Download and install the licensing server. To install the licensing server : NLICMGR-11.7.0-x86_64-linux.tar.gz The package contains scripts to install and uninstall the included RPM.

Copy the package on the host machine.

Change to the directory and untar the package. For example:

```
#tar -zxvf NLICMGR-11.7.0-i686-linux.tar.gz
```

Run the installation script:

```
#./install.sh.
```

The default installation path for licensing software is `usr/local/Nuance/license_manager`.

```
Copyright © 2015, Nuance Communications, Inc. All rights reserved.
```

```
Welcome to the Nuance License Manager 11.7.0-12057 Installation.
```

```
The product will be installed in the /usr/local directory
```

```
To specify a different directory, type an absolute  
path below and press the [Enter] key.
```

```
To accept the default directory of /usr/local,  
press the [Enter] key.
```

```
Installing Nuance License Manager 11.7.0-12057
```

```
Preparing... #####  
[100%]
```

```
1:nuance-licmgr #####  
[100%]
```

```
Nuance License Manager 11.7.0-12057 was successfully installed  
to /usr/local/Nuance/license_manager
```

```
Visit the Nuance Network Customer Service Portal (http://network.nuance.com)  
for updates and the latest release notes.
```

Configure a license file.

You need to install a license file using the script provided by Nuance.

The Nuance script changes the filename expected by the licensing server, and restarts licensing server to use the new filename. Do the following:

Copy the new license file to `/usr/local/Nuance/license_manager/components/license/new_filename.lic`

Change directory to `/usr/local/Nuance/license_manager/components`

Run the script `set-new-lic-file.sh`. The usage format is: `set-new-lic-file.sh full_path_to_new_license_file`

For example:

```
#cd /usr/local/Nuance/license_manager/components  
#./set-new-lic-file.sh /nuance/license_manager/license/my.lic
```

To replace the current license file using FLEXnet tools, put the new license file in a secure disk location (Nuance recommends using a different name for each license file), use `lmtools` or `install.exe` to point the licensing server to the new file, and restart the licensing server. The tools are in `install_path/components`, and are described in the FLEXnet documentation (see `install_path/doc/LicensingEndUserGuide.pdf`).

Start the licensing server. The licensing server starts automatically when you restart the host machine. The service name is "Nuance License Server." The service runs the script `/etc/rc.d/init.d/nuance-licmgr`, which calls the License Server Daemon with the appropriate command options. This service is created and configured during installation using the template `install_path/components/nuance-licmgr`. The root user can manually stop and start the licensing server, and can perform a restart:

```
> /etc/rc.d/init.d/nuance-licmgr start  
> /etc/rc.d/init.d/nuance-licmgr stop  
> /etc/rc.d/init.d/nuance-licmgr restart
```

When installing Nuance licensed products, administrators must configure the number of licenses checked out by that product at runtime

Install the Recognizer

Packages/files

- License : `sdk-eval-recognizer10_license.lic`
- Recognizer : `NRec-10.2.6-x86_64-linux.tar.gz`
- Languages : `NRec-en-US-10.0.0-10.0.0.i686-linux.tar.gz`

Licensing Recognizer

Move the Recognizer evaluation license to `/usr/local/Nuance/license_manager/license`. Merge together the two license files (Vocalizer and Recognizer) by copying in one of them the INCREMENTS from the other one and save the combined file with a new name (e.g. `nve6_nr10_eval.lic`). Goto `/usr/local/Nuance/license_manager/components` and run the command

```
./set-new-lic-file.sh  
/usr/local/Nuance/license_manager/license/nve6_nr10_eval.lic
```

Install the engine

Change directory to the location of the downloaded software, and extract the archive:

```
#tar -zxf NRec-xxxxx.tar.gz
```

The tar command extracts the installation files to a Nuance_Recognizer subdirectory.

Run the install.sh script:

```
#cd Nuance_Recognizer
#./install.sh
```

Copyright © 2015, Nuance Communications, Inc. All rights reserved.

Welcome to the Nuance Recognizer 10.2.6-14289 Installation.

The product will be installed in a /Nuance/Recognizer product directory in the /usr/local default parent directory.

To specify a different directory, type an absolute path below and press the [Enter] key.

To accept the default parent directory of /usr/local, press the [Enter] key.

Installing Nuance Recognizer 10.2.6-14289

```
Preparing... #####
[100%]
  1:Nuance-Common64 ##### [
33%]
  2:NRec ##### [
67%]
  3:Nuance-NRS64 #####
[100%]
```

Nuance Recognizer 10.2.6-14289 was successfully installed to /usr/local/Nuance/Recognizer.

Visit the Nuance Network Customer Service Portal (<http://network.nuance.com>) for updates and the latest release notes.

The command format for installing NRS as a daemon is:

```
#cd /usr/local/Nuance/Recognizer_Service/amd64/bin
#./NRSservice.sh
```

Start Recognizer Server :

```
#/etc/init.d/NRSservice start
Starting NRSserver: [ OK ]
```

Install the languages

You must install at least one language after you install the Nuance Recognizer. The first language installed becomes the default language.

Change directory to the location of the downloaded software, and extract the archive:

```
#tar -zxf NRec-en-GB-xxxxxx.i686-linux.tar.gz
```

The tar command extracts the installation files to a subdirectory named for the language, for example, NRec-en-GB-10.0.0-10.0.0.

Change directory to the language subdirectory, and run the install.sh script.

```
#./install.sh
```

```
Copyright © 2015, Nuance Communications, Inc. All rights reserved.
```

```
Welcome to the Nuance Recognizer English en-GB 10.0.0-10.0.0 Language Pack
installation.
```

```
Installing the Nuance Recognizer English en-GB 10.0.0-10.0.0 Language Pack
```

```
Preparing... #####
```

```
[100%]
```

```
1:NRec-en-GB-10.0.0 #####
```

```
[100%]
```

```
The Nuance Recognizer English en-GB 10.0.0-10.0.0 Language Pack was
successfully installed to the /usr/local/Nuance/Recognizer/config directory.
```

```
Visit the Nuance Network Customer Service Portal (http://network.nuance.com)
for updates and the latest release notes.
```

Repeat this actions for each language.

Testing the recognizer stand-alone

Further configure the system by running the following command source /usr/local/Nuance/Recognizer/SETUP-env.sh At last, to test the system, run the following command. Go to the directory /usr/local/Nuance/Recognizer/samples/swirec_sample/ and run the executable :

```
./SWIrecSample
```

```
In the middle of its long output you should find the following
XML result is =
```

```
<?xml version='1.0'?>
```

```
<result>
```

```
<interpretation grammar="DTMF_Grammar" confidence="100">
```

```
<input mode="dtmf">6 1 7 4 2 8 4 4 4 4</input>
```

```
<instance>
  <SWI_meaning>6174284444</SWI_meaning>
  <RESULT confidence="100">6174284444</RESULT>
  <SWI_literal>6 1 7 4 2 8 4 4 4 4</SWI_literal>
  <SWI_grammarName>DTMF_Grammar</SWI_grammarName>
</instance>
</interpretation>
</result>
```

This is the demonstration the system is working properly.

Install Nuance Speech Server

To install the server software on the server machine:

Confirm that all prerequisite software is installed.

Download the Nuance Speech Server product from Nuance Network at network.nuance.com.

Extract the downloaded software: `tar -zxf NSS-version_number-i686-linux.tar.gz`

Change directory:

```
#cd Nuance_Speech_Server
```

Run the installation script:

```
#./install.sh
```

The installer prompts you to accept the default installation directory (`/usr/local`) or to specify an alternate absolute path.

```
Copyright © 2015, Nuance Communications, Inc. All rights reserved.
```

```
Welcome to the Nuance Speech Server 6.2.7-14290 Installation.
```

```
The product will be installed in the /usr/local directory
```

```
To specify a different directory, type an absolute
path below and press the [Enter] key.
```

```
To accept the default directory of /usr/local,
press the [Enter] key.
```

```
Installing Nuance Speech Server 6.2.7-14290
```

```
Preparing... #####
[100%]
```

```
1:Nuance-Common ##### [
25%]
2:Nuance-Doc ##### [
50%]
3:Nuance-OAM ##### [
75%]
4:NSS #####
[100%]
```

Creating the NSSserver.cfg configuration file ...

Installing the NSS service ...

Reloading httpd:

Nuance Speech Server 6.2.7-14290 was successfully installed
to /usr/local/Nuance/Speech_Server/server.

Visit the Nuance Network Customer Service Portal (<http://network.nuance.com>)
for updates and the latest release notes.

Start Speech Server .:

```
# /etc/init.d/nuance-wd start
Starting nuance-wd: [ OK ]
# /etc/init.d/NRSservice start
Starting NRSserver: [ OK ]
# /etc/init.d/NSSservice start
Starting NSSserver: [ OK ]
```

After installation finishes, perform basic configuration described in [Configuring the system](#).

From:
<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:
https://wiki.voximal.com/doku.php?id=legacy:speech_recognition_guide:nuance_asr:start

Last update: **2017/07/28 23:33**

