

System Management

Getting Started

Once you have completed installing the VoiceXML browser, you must configure the VoiceXML browser before attempting to place calls. The management and configuration procedures completely depend on the integration, as the reference VoiceXML browser components never directly access a configuration subsystem. Instead, all configuration parameters are passed to the initialization or resource creation functions for each VoiceXML browser component. OpenVXI is an old portable open source VoiceXML interpreter and is a part of Vxi. The Vxi VoiceXML browser is configured through a text configuration file specified on the command line. Each line of this file defines a value for a property (parameter) applying to a given OpenVXI component; the possible property names are defined in the interface header files for the various components. The configuration file format is described in detail in a comment block at the top of the sample configuration file, `/etc/vxmld.conf` (old version: `/etc/openvxi/client.cfg`).

NOTE:

Before any configuration update, make a backup copy of your `client.cfg` file.

Once you have made a backup copy, review the properties in the configuration file and modify their settings as appropriate. For an explanation of each property, refer to support. In most cases you can modify the following properties to get started (listed in priority order):

Configure the internet access to use http
Configure the cache management
Activate/ deactivate traces
Configure the supported MIME types

Cache Management

In the Client configuration section, set `client.inet.cacheDir` to the directory where you want to store cached Internet files from URL fetches. Set the `client.inet.cacheTotalSizeMB` property to the desired size limit in megabytes for the Internet fetch cache. Processing VXI* produces standard traces under the `/tmp/log.txt` file. The trace file names are referenced in the `/etc/vxmld.conf` (old versions: `/etc/openvxi/client.cfg`) file. Their format can be found in the Log Files section of this document.

NOTE:

To disable the cache entry, set the `maxage` and `maxstale` properties to 0. This properties can be change in the `default.xml` file to globally disable the cache.

Webserver Configuration (optional)

The VXI* VoiceXML browser supports running against static content stored as local files as well as static or dynamic content served by a web server. The VoiceXML browser is generally used with a web

server. Content can be VoiceXML documents, audio / images / video files (if supported by your version or license), and grammar files. When a web server delivers the content, it also provides the MIME content type for the content and information about the desired caching behavior for the content. For the MIME content type for VoiceXML documents, a value of application/vxml+xml is recommended, but not mandatory, as the VoiceXML browser can use information within the XML document to verify it is a VoiceXML document. For prompt, recognize and record interfaces the MIME content type is more important. Support for the following audio formats is recommended for play and record operations, but not mandatory.

MIME Content	Type Description
audio/basic	RAW (headerless) 8kHz 8-bits mono mu-law [PCM] single channel. (G.711)
audio/x-alaw-basic	RAW (headerless) 8kHz 8-bits mono A-law [PCM] single channel. (G.711)
audio/x-wav	WAV (RIFF header) 8kHz 16-bits mono [PCM] single channel.
audio/X-WAV	WAV (RIFF header) codec GSM (6.10) 7-bits mono single channel.
audio/x-gsm	GSM (6.10) 7-bits mono single channel.
video/mp4	MP4 (Iso file) H.263 7 fps, mulaw/alaw/AMR-NB
video/3gp	3GP (Iso file) H.263 7fps, AMR-NB

The length of time the VoiceXML browser caches an item fetched from a web server is controlled by the caching values returned in the HTTP/1.1 header. The VoiceXML browser currently only supports the “Expires” header, which defines the date and time when the VoiceXML browser must discard the cached copy and re-fetch from the web server. Some web servers allow defining caching property defaults based on the MIME content type, useful for allowing caching of audio files but not dynamically generated VoiceXML documents, for example.

Start/Stop Vxi

The VoiceXML browser software is installed in /usr/sbin and /usr/lib/opencvxi. The VoiceXML browser setup script on Linux is /etc/init.d/opencvxi. The opencvxi script calls the /usr/sbin/safe_opencvxi executable that functions as a monitor and auto-loader for your VoiceXML browser system. This safe_opencvxi starts the VoiceXML browser and monitors it to make sure it is still running. If the VoiceXML browser process dies, the script will attempt to restart it. To load or unload the VoiceXML browser, use the “opencvxi start” and “opencvxi stop” commands:

```
#/etc/init.d/opencvxi start
#/etc/init.d/opencvxi stop
```

Starting processes at boot time are different among the different operating systems so it is best to consult your OS documentation on how to do this. In Debian-based systems you can add this to your /etc/init.d file, however this will not shutdown the VoiceXML browser very cleanly during a reboot or shutdown. In a Debian environment you may be able to get a working /etc/init.d script by running the following commands. It will then run the following command:

```
#!/sbin/chkconfig --add opencvxi
```

Using Vxi

The Vxi VoiceXML browser installs the app_vxml Asterisk application that uses the browser to execute VoiceXML pages.

Check the VXML application module For more information on applications, just type “show application” at the Asterisk CLI prompt. To show details of how you use that particular application in this file (the Asterisk Dial plan).

Type:

```
*CLI> show application <command>
```

For example, the vxml application:

```
*CLI> show application vxml
```

Usage Syntax

Description:

Launch a VoiceXML session in the channel and when complete, return control.

The URL can be set with different ways :

```
Pass the URL as the application parameter. Exemple :  
vxml(file://tmp/test.vxml)  
Pass the account name or the account number. Exemple: vxml(test)  
Pass the “@” to match the caller number to the account number.
```

Set the VXML_URL variable before executing the vxml application. Don't pass any parameter, and use the configuration accounts section. If account number match with the called number, its URL(s) and parameters will be use.

The following describes how to execute a VoiceXML session.

Syntax:

```
Vxml ( [ URL | Name | Number ] )
```

Variables:

VXML_URL

If the variable VXML_URL has been set when vxml runs, the value of that variable will be used for the URL unless the parameter is not set to the application.

VXML_ID

If the variable VXML_ID has been set when vxml runs, the VoiceXML session ID variable called “telephone.id” is set with this value (in the VoiceXML execution session context).

VXML_PARAM

If the variable VXML_PARAM (VXML_AAI is an alias) has been set when vxml runs, the value of that variable will be used as “telephone.param” (in the VoiceXML execution session context) and session.connection.aai.

VXML_RESULT

After execution, the VoiceXML result of <exit> tag and the property ‘expr’ are accessible by the variable VXML_RESULT.

Example:

```
[incoming]
exten => s,1,Answer
exten => s,n,Wait(3)
exten => s,n,Vxml(http://vxml.i6net.com/index.vxml)
exten => s,n,Hangup
```

Asterisk Online Help

Online help can be accessed by typing the following command at the CLI prompt: *CLI> help vxml

Management Commands

Now your VXi* VoiceXML browser and Asterisk PBX are running, you can manage the VXML service using the Asterisk prompt *CLI>:

```
*CLI> vxml debug
```

Enable VoiceXML debugging for the Asterisk application.

```
*CLI> vxml debug interpreter all
```

Enable VoiceXML debugging for the interpreter application ().

```
*CLI> vxml no debug
```

This command disables VoiceXML debugging for the Asterisk application.

```
*CLI> vxml no interpreter debug
```

This command disables VoiceXML debugging for the interpreter application.

```
*CLI> vxml show cache / vxml cache show
```

Print the files in cache (if debug mode is enabled) and/or the number of file in the cache.

```
*CLI> vxml cache clear
```

Delete all the files in the cache.

```
*CLI> vxml cache purge
```

Delete all the files in the cache older than the maxage parameter set in the configuration.

```
*CLI> vxml show license
```

Use this command to show the license information.

```
*CLI> vxml reload
```

Reload the configuration.

```
*CLI> vxml show configuration
```

Use this command to show the configuration summary of VoiceXML interpreter.

```
*CLI> vxml show accounts
```

Show the accounts configured.

```
*CLI> vxml show account <number>
```

Show the accounts details of the account ID specified.

```
*CLI> vxml show statitiscs
```

Provides a dump statistics on VoiceXML interpreter

```
*CLI> vxml show dates
```

Provides a dump dates on VoiceXML interpreter

*CLI> vxml show sessions </code> Provides a dump sessions on VoiceXML interpreter.

```
*CLI> vxml show session
```

Provides a full dump session on VoiceXML interpreter.

```
*CLI> vxml originate chantype/number=application(parameters)
```

Originate an outgoing call, you can request to use a VoiceXML session.

The following entries are the Asterisk CLI commands for the VoiceXML browser.

Example: Add extensions to the Asterisk dial plan `/etc/asterisk/extensions.conf`:

```
exten => 888,1,Answer  
exten => 888,n,Wait(3)  
exten => 888,n,Vxml(file:///root/example.vxml)  
exten => 888,n,Hangup
```

You can create and edit the file `/root/example.vxml` with the GNU text editor, VI, for example.

NOTE:

This example will work if you have text-to-speech configured. If not, use a pre-recorded wav or gsm file to replace the "Hello world!" text by an `<audio>` tag. For more information, see the format extensions supported by Asterisk.

```
<block><audio src="hello.wav"/></block>
```

Save the file in the same directory as the VoiceXML script (relative reference in this example). Reload the extensions configuration with: `*CLI> extensions reload`

Call the service by calling:

```
SIP:888@<your server address>
```

Troubleshooting (for Support)

This chapter covers troubleshooting procedures for the VoiceXML Browser, describing some basic techniques that can be used when working with Vxi.

Collecting Information for Technical Support As part of the process of reporting problems, download log files and core files from the VoiceXML Browser and send them to I6NET, together with the current configuration files.

```
/tmp/log.txt (default configuration)
```

Core files

Collected files should be sent by email to Technical Support (support@i6net.com).

Log Files

The log files contain information about the operation of the VoiceXML Browser. The file is `/tmp/log.txt`, which details the VoiceXML processing on the VoiceXML Browser. If a failure occurs and you need to contact I6NET support (at support@i6net.com), they may ask you to activate traces to allow analysis of the system functions and make a complete appraisal of the problem. To do so you must follow these

procedures:

Edit the configuration file `client.cfg` in `/etc/openvxi/`. The levels are defined by these lines which are the # API/general log traces for each component:

<code>client.log.diagTag.2000</code>	<code>VXIInteger</code>	<code>0</code>
<code>client.log.diagTag.2001</code>	<code>VXIInteger</code>	<code>0</code>
<code>client.log.diagTag.3000</code>	<code>VXIInteger</code>	<code>0</code>
<code>client.log.diagTag.3001</code>	<code>VXIInteger</code>	<code>0</code>
<code>client.log.diagTag.3002</code>	<code>VXIInteger</code>	<code>0</code>

The ranges are associated to different interfaces:

<code>200x:</code>	Cache interface
<code>300x:</code>	Internet HTTP interface
<code>400x:</code>	ECMAScript interface
<code>500x:</code>	Prompt interface
<code>600x:</code>	Recognize interface
<code>700x:</code>	Telephony/Session interface
<code>800x:</code>	XML Interpreter
<code>900x:</code>	Object interface
<code>1000x:</code>	Main/Client application

To enable a level, set the 1 value and 0 to disable. To validate the modifications, the VoiceXML interpreter must be restarted. A simple way to do this is to stop and restart this application with the Asterisk and OpenVXI script:

```
# /etc/init.d/asterisk stop
# /etc/init.d/openvxi stop
# /etc/init.d/openvxi start
# /etc/init.d/asterisk start
```

The log file is generated in the temporary directory, and is named `log.txt`. The location and filename are configurable. To purge the file type:

```
# > /tmp/log.txt
```

NOTE:

1. Never delete the `/tmp/log.txt` directly, otherwise you should restart the VoiceXML browser to generate a new one.
2. An Apache/PHP script exists generate the traces from a standard Internet browser (Internet Explorer, Mozilla/firefox...). Get it from our web site
3. At the end of the trace record, don't forget to stop it to recover optimal real time function. With the V4.x release, you can dynamically enable/disable the interpreter traces with an Asterisk *CLI> command.

Simple traces for the VoiceXML development:

```
*CLI> vxml debug interpreter dev
```

Full traces:

```
*CLI> vxml debug interpreter all
```

Disable the interpreter traces:

```
*CLI> vxml no debug interpreter
```

Restore the log traces:

```
*CLI> vxml debug interpreter log
```

Current Sessions To determine how many VoiceXML sessions are currently active on the system, use the statistics dump on the CLI. This command displays the current number of sessions on the VoiceXML Browser:

```
*CLI> vxml show statistics
```

File descriptors To find out how many file descriptors are being used follow this:

Find out program PID:

```
# ps -ef | grep asterisk
```

Find out program PID (other command):

```
# pidof asterisk
```

List of files opened by PID (details):

```
# ls -l /proc/[PID]/fd
```

List of files opened by PID (counter):

```
# ls -l /proc/[PID]/fd | wc -l
```

More information about file descriptors:

```
# lsof | grep "[PID]"
```

From:
<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:
https://wiki.voximal.com/doku.php?id=vxi_installation_guide:management:start&rev=1422018500

Last update: **2017/07/28 22:29**

