Soft Phone connection

Set up a software telephone so that you can play with Voximal. We recommend Zoiper or YateClient which are free. Download them from :


- IaxLite (old windows application)
- https://www.zoiper.com/en/voip-softphone/download/zoiper-classic/for/windows (freeware with commercial offer)
- YateClient (opensource freeware)

Account datas :

- username : user
- password : (get it form the Voximal/Settings/Test)
- server : (the IP adress of your server)

Get your password from the Web Interface

Select Setting → Voximal Setting → Test



Get your password from the Asterisk console

Execute :


```
raspbx*CLI> voximal show license
Version       : V14.0
Build
```

```
 CVS Revision : $Revision: 1.853 $
 Gcc          : V4.9
 Arch         : 32 bits
 Target       : i686
 Asterisk     : V13.11.2
 Options sum  :
 Date         : Nov  3 2016 21:40:06
Code          : b6de76bcb827eb415eb3b6f75b1001
UID           : cb773b52-a362-11e6-af57-b827eb415eb3
PIN           : 3152
Password      : cb773b52
Key           :
Max sessions  : 1
Options
 TextToSpeech : Yes
 Speech       : Yes
State         : ok
```

Your password is : **cb773b52**


IaxLite

- Run IAXLite once you've installed it and enter the credentials for the account on your Voximal. You'll need the IP address of your server and your extension 'user' password.
- Click the **[Set.]** button.
- Fill in the blanks using the IP address of your server, 'user' for your account name, and whatever password got from your Voximal installation server.



Zoiper

- Run Zoiper once you've installed it and enter the credentials for the account on your Voximal. You'll need the IP address of your server and your extension 'user' password.
- Choose Settings → Accounts and click the **[Create Account]** button.
- Select IAX.
- Fill in the blanks using the IP address of your server, 'user' for your account name, and whatever password got from your Voximal installation server.




YateClient

- Run YateClient once you've installed it and enter the credentials for the 'user' extension on

Voximal. You'll need the IP address of your server plus your extension user password.

- Choose Settings → Accounts and click the **[New]** button.
- Fill in the blanks using the IP address of your server, 'user' for your account name, and whatever password got from your Voximal installation server.



From:
https://wiki.voximal.com/ - **Voximal documentation**

Permanent link:
https://wiki.voximal.com/doku.php?id=installation_guide:softphone:start&rev=1525692364

Last update: **2018/05/07 11:26**