

# VoiceInteraction ASR

## About

VoiceInteraction  
Rua Alves Redol, 9  
1000-029 Lisboa  
Portugal

Website: <http://www.voiceinteraction.pt>

## Definition

VoiceInteraction, founded in 2008 and based in Lisboa (Portugal), is a company specialised in the development of speech technologies. VoiceInteraction develops voice synthesis and speech recognition engines for many web and telephony applications.

## Languages

Portuguese · Portuguese (Brazil)

## Installation

This is for the Debian Lenny version, for other Linux, read the official Audimus Installation manual. To configure the apt client, just edit and add to the file `/etc/apt/sources.list` one of the following line set.

For asterisk 1.Y.X

```
deb http://services.voiceinteraction.pt/repo/Debian/5.0 engines 3rdparty  
Dixi Audimus  
deb http://services.voiceinteraction.pt/repo/Debian/5.0 asterisk.1.Y.X Dixi  
Audimus
```

Refresh the package local base with:

```
# apt-get update
```

And Install the package `audimus-asterisk-xx-xx` (where `xx-xx` is the language requested):

```
# apt-get install audimus-asterisk-es-es
```

The following extra packages will be installed:

```
audimus audimus-config audimus-model-es-es-monophones-g2p-phonemodels
audimus-model-es-es-monophones-mlp-telephone audimus-model-es-es-monophones-
task-asterisk
```

Activate the license with:

```
# audimus_activate_license
```

Please enter your Audimus license:

```
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
Your License was successfully activated!
```

## Configuration

To enable speech recognition, change the main speech parameter. The "speech" parameter can get three values, "yes", "automatic", "no" or "emulation" (don't generate errors if you enable speech grammars).

```
...
speech=automatic
speechprovider=verbio
...
```

In the VoiceXML browser configuration file:

```
#####
# ASR server configuration #
#####

client.rec.resource.0.cacheDir      VXIString  /tmp/cacheContent
client.rec.resource.0.format        VXIString  txt
client.rec.resource.0.syntax        VXIString  doctype
```

You need to restart the Vxi and Asterisk to get all the changes.

Logs file from the ASR engine:

```
# tail -f /var/log/VI/VI.log
```

The following VoiceXML example uses the speech recognition, with the built in grammar, 'digits.'

```
<?xml version="1.0" encoding="iso-8859-1"?>
<vxml version="2.0" xmlns="http://www.w3.org/2001/vxml" xml:lang="en-UK">
  <form>
    <property name="inputmodes" value="voice"/>
    <property name="timeout" value="30s"/>
```

```
<field name="text" type="digits">  
  <catch event="noinput nomatch">  
    <reprompt/>  
  </catch>  
  <prompt>  
    Speak to me:  
  </prompt>  
</field>  
<filled>  
  <prompt>  
    You say me:  
    <value expr="text" />  
  </prompt>  
  <clear namelist="text" />  
</filled>  
</form>  
</vxml>
```

From:  
<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:  
[https://wiki.voximal.com/doku.php?id=legacy:speech\\_recognition\\_guide:voiceinteraction\\_asr:start](https://wiki.voximal.com/doku.php?id=legacy:speech_recognition_guide:voiceinteraction_asr:start)

Last update: **2017/07/28 23:33**

