

# Verbio TTS

## About

### Verbio Technologies

Loreto 44  
08029 Barcelona  
Spain

Website: <http://www.verbio.com>

## Definition

Verbio is a company based in Barcelona (Spain), specializing in speech technologies, aimed basically at the Spanish, Portuguese and Latin American markets.

## Languages

English (US) · French · Portuguese · Portuguese (Brazil) · Spanish(Argentina) · Spanish (Chile) · Spanish (Venezuela) · Spanish (Colombia) · Spanish (Cuba) · Spanish (Santo Domingo) · Spanish (Puerto Rico) · Spanish (Paraguay) · Spanish (Uruguay) · Spanish(Mexico) · Spanish (North America) · Spanish (Catalan) · Spanish (Valencia) · Spanish (Galician) · Spanish (Euskera)

## Installation

If your distribution does not use 'rpm' nor 'deb' please us to get specific installation packages or support.

Download the TTS binaries packages after contacting the Verbio sales.

```
# dpkg -i verbio-engines-x.yy.deb
# dpkg -i --force-overwrite verbio-clients-x.yy.deb
# dpkg -i --force-overwrite verbio-tts-*-x.yy.deb
# dpkg -i --force-overwrite verbio-asr-*-x.yy.deb (for the ASR)
```

If you have a license in a USB token, you need to install the USB token driver ('sntl-sud\_x.y.z-w\_i386.deb').

You will find the sntl package at:

```
/usr/share/doc/verbio
```

Then you start with:

```
# cd /usr/share/doc/verbio
# dpkg -i sntl-sud_7.3.0-1_i386.deb
```

You need to reboot the server to enable the USB daemon ().

If you have a file licence, please copy it to:

```
/opt/verbio/lic/
```

Download and install our connector package for Verbio.

First unzip and untar it by using the command:

```
# tar xvzf verbio_Vx.x_date.tar.gz
```

Next, go to the directory of the Verbio and type the following command:

```
# cd verbio_Vx.x_date
# ./install.sh
```

## Configuration

The TTS package install the HTTP scripts in:

```
/var/www/tts/verbio
```


In a default Debian installation, you can test the TTS installation at:

```
http://yourip/tts/verbio/tts.html
```

This web page will generate your TTS raw alaw or ulaw files.

## Release Notes

Install the script on your Apache/PHP server. Configure the VoiceXML Browser (Text-to-Speech Option) and restart the VoiceXML interpreter to get the new configuration.



From:

<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:

[https://wiki.voximal.com/doku.php?id=legacy:text-to-speech\\_guide:verbio\\_tts:start](https://wiki.voximal.com/doku.php?id=legacy:text-to-speech_guide:verbio_tts:start)



Last update: **2017/07/28 23:34**