

Active a Voxibot Amazon AWS image



- **Web site** : <https://aws.amazon.com/>

Amazon Web Services (AWS) is a secure cloud services platform, offering compute power, database storage, content delivery and other functionality to help businesses scale and grow. Explore how millions of customers are currently leveraging AWS cloud products and solutions to build sophisticated applications with increased flexibility, scalability and reliability.

[Getting started with AWS](#)

- **List of EC2 Images (AMI)**

EC2 Regions	Latest Voxibot for Linux Amazon
ap-northeast-1	ami-9039e2f1
ap-northeast-2	ami-cda175a3
ap-southeast-1	ami-1364c370
ap-southeast-2	ami-74546617
eu-central-1	ami-01a45a6e
eu-west-1	ami-95d497e6
sa-east-1	ami-ac1785c0
us-east-1	ami-2bc1883c
us-west-1	ami-fdeca59d
us-west-2	ami-67bd6607

- **Installation (with a Voximal Images) : Soon available**

1. If you haven't already set up an Amazon Web Services account, you must do so in order to use the Amazon Cloud Images.
2. Go to [Amazon Management Console](#)
3. Sign in to the AWS Console.
4. Go to Security Groups section and update your default group. Make sure you have ports TCP/80 (HTTP) add other ports like TCP/22 (SSH) and UDP/4569 (IAX2) to be able to use the Voximal in your EC2 instance. You can add it as shown below - click Save at the end.
5. Go to the AMIs section and find all "**Voximal**". Select the option "Public Images" in the "Viewing" selector. Fill in the filter field with the "bitnami" string or you may also try to look for the the latest version putting the identifier shown in the Bitnami download page "ami-...".
6. Choose one of the images and click the right mouse button to show the list, choose Launch instance.

- **Installation (with a Linux Amazon AMI) :**

1. If you haven't already set up an Amazon Web Services account, you must do so in order to use the Amazon Cloud Images.
2. Go to [Amazon Management Console](#)
3. Sign in to the AWS Console.
4. Go to Security Groups section and update your default group. Make sure you have ports TCP/80 (HTTP) add other ports like TCP/22 (SSH) and UDP/4569 (IAX2) to be able to use the Voximal in your EC2 instance. You can add it as shown below - click Save at the end.
5. Go to the AMIs section and find all "**Linux Amazon AMI**". Select the option "Public Images" in the "Viewing" selector. Fill in the filter field with the "bitnami" string or you may also try to look for the the latest version putting the identifier shown in the Bitnami download page "ami-...".
6. Choose one of the images and click the right mouse button to show the list, choose Launch instance.
7. To connect you need to use a key (for Windows/Putty user you need to convert the pem to ppk).
8. Connect to SSH to complete the installation with the Voximal installer package : [Installation of Voximal](#).

Test your installation

You have two simple ways to test and validate your installation :

- With a soft phone : [Soft Phone connection](#)
- With the test numbers : [Call the test service](#)

From:
<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:
https://wiki.voximal.com/doku.php?id=cloudproviders:amazon_aws&rev=1478511855

Last update: **2016/11/07 09:44**

