

Install the Voxibot Suite or add the Voximal Module

To install your Voximal application you have 2 ways :

- To install the Voximal suite from a new linux server, select the Voxibot suite package. It installs Asterisk/FreePBX/Voxiaml to produce a ready to go Voximal server.

Voxibot Suite

- To install the Voximal application from a FreePBX or Asterisk server, select the Voximal module. It install the Voximal VoiceXML browser on your Asterisk configuration. If you use the FreePBX interface, you will see a FreePBX module to manage the VoiceXML application from the FreePBX interface (settings, application, logs, status...).

Voximal Application

Voximal : Installation over a Asterisk/FreePBX/Elsatix/Xivo



The Voximal module package install :

- Voximal V14.x

Supported Linux Distributions :

- Linux Centos 6 32/64bit
- Linux Centos 7 32/64bit
- Linux Ubuntu 14.0
- Linux Debian 8 32/64bit
- Linux Raspbian 8 Arm

Dependencies

- Asterisk 1.6 ... 14.beta
- (FreePBX 12 for the GUI/Web configuration interface)

Note : You need to disable linuxSE (if you already installed Asterisk it should already done).

Note : You need the tar and gzip tools already installed on your server.

Then:

1. You need to be root to process the installation.
2. Change the permission to execute the installer script (execute "chmod +x voxibot*").
3. Execute the script and follow the instructions (generally answer 'y' for each questions).
4. When done, connect to <https://myserver/admin> - you will be asked for login.
5. Login using as user user password user.

Screen shot:

```
[root]# ./voximal.x.xx_2016xxxx_0voximalxxcentos6_all.run
Creating directory voxibot_1.x.xx_2016xxxx_0voximalxxcentos6_all
Verifying archive integrity... 100% All good.
Uncompressing Voxibot bundle 1.x.xx 100%

Version 1.x.xx

Installation Database      [ OK ]
Installation Web_Server   [ OK ]
Installation Telephony    [ OK ]
Installation Framework    [ OK ]
Installation Interpreter  [ OK ]
Installation Ressources    [ OK ]

Installation complete

To access the Web interface browse to :
    http://<your_machine_ip>/admin (login 'user' and password 'user')

[root]#
```

From:

<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:

https://wiki.voximal.com/doku.php?id=installation_guide:installation:start&rev=1473886671

Last update: **2016/09/14 20:57**

