

Soft Phone connection

Set up a software telephone so that you can play with Voximal. We recommend Zoiper or YateClient which are free. Download them from :


- [laxLite](#) (old windows application)
- <https://www.zoiper.com/en/voip-softphone/download/zoiper-classic/for/windows> (freeware with commercial offer)
- [YateClient](#) (opensource freeware)

Account datas :

- username : user
- password : (get it form the Voximal/Settings/Test)
- server : (the IP adress of your server)

Get your password from the Web Interface

Select Setting → Voximal Setting → Test



The screenshot shows the Voximal web interface. At the top, there is a navigation bar with links for 'Voximal', 'Connectivity', 'Reports', 'Settings', and 'Apply Config'. The 'Settings' menu is expanded, showing 'Voximal Settings'. Below this, there are four tabs: 'General', 'TextToSpeech', 'License', and 'Call Test'. The 'Call Test' tab is selected. The main content area contains the following text:

An easy way to make tests.
To call your Voxibot :
Call the +33(0)972538823 and enter the PIN number.

PIN	?
Port number	4569

At the bottom of the page, there is a footer with the text 'Version 1.0.121 18 Oct 10:10:11', the 'voximal' logo with the tagline 'The voice interaction', and a 'Support' link.

Get your password from the Asterisk console

Execute :


```
raspbx*CLI> voximal show license  
Version      : V14.0  
Build
```

```
CVS Revision : $Revision: 1.853 $
Gcc          : V4.9
Arch         : 32 bits
Target       : i686
Asterisk     : V13.11.2
Options sum  :
Date         : Nov  3 2016 21:40:06
Code         : b6de76bcb827eb415eb3b6f75b1001
UID          : cb773b52-a362-11e6-af57-b827eb415eb3
PIN          : 3152
Password     : cb773b52
Key          :
Max sessions : 1
Options
  TextToSpeech : Yes
  Speech       : Yes
State         : ok
```

Your password is : **cb773b52**


IaxLite

- Run IAXLite once you've installed it and enter the credentials for the account on your Voximal. You'll need the IP address of your server and your extension 'user' password.
- Click the **[Set.]** button.
- Fill in the blanks using the IP address of your server, 'user' for your account name, and whatever password got from your Voximal installation server.



Zoiper

- Run Zoiper once you've installed it and enter the credentials for the account on your Voximal. You'll need the IP address of your server and your extension 'user' password.
- Choose Settings → Accounts and click the **[Create Account]** button.
- Select IAX.
- Fill in the blanks using the IP address of your server, 'user' for your account name, and whatever password got from your Voximal installation server.



YateClient

- Run YateClient once you've installed it and enter the credentials for the 'user' extension on

Voximal. You'll need the IP address of your server plus your extension user password.

- Choose Settings → Accounts and click the **[New]** button.
- Fill in the blanks using the IP address of your server, 'user' for your account name, and whatever password got from your Voximal installation server.

The screenshot shows a dialog box titled "Edit account: iaxuser@192.168.1.28". It contains the following fields and controls:

- Use provider:** A dropdown menu with the value "-none-".
- Protocol:** A dropdown menu with the value "iax".
- Username:** A text input field containing "user".
- Password:** An empty text input field.
- Save password:** An unchecked checkbox.
- Server:** A text input field containing "192.168.1.28".
- Domain:** An empty text input field.
- Outbound proxy:** An empty text input field.
- Registration Interval:** An empty text input field.
- Advanced >>** A button to expand the form.
- Ok** and **Cancel** buttons at the bottom left.
- A help icon (?) at the bottom right.

From: <https://wiki.voximal.com/> - **Voximal documentation**

Permanent link: https://wiki.voximal.com/doku.php?id=installation_guide:softphone:start&rev=1525692364

Last update: **2018/05/07 11:26**

