

# Call the test service

You can test your Voximal installation by calling the test numbers from any phone.

We setup 2 phone numbers :

- France : +33(0)9 72 53 88 23
- Unites States : +1-202-600-4534

You need to open the port 4569 from/to the internet. The calls will be transfered by this way to your Voximal server to the number/extension :

- **8965** ('VXML' from your phone dialpad).

By default, the Voximal installation configures the 'helloworld' service/account that executes this VoiceXML document :

- [helloworld.vxml](#)

When you call the voice portal, the service will request your PIN number.

## Get your PIN from the Web Interface


With the Voxibot solutio, the PIN number is in the main panel :

The screenshot displays the Voximal web interface. The top navigation bar includes 'Voximal', 'Reports', 'Settings', and a 'Logout: admin' button. The main content area is divided into several panels:

- System Overview:** Displays 'Welcome to ip-172-31-40-237' and a test instruction: 'Test : Call +33(0)972 538 823 and enter your PIN 2643'. It includes a summary table with status indicators for Telephony, Database, Web Server, and Interpreter. A green box indicates 'System Alerts: No critical issues found'. A blue box shows 'There are 2 bad destinations'.
- Uptime:** Shows 'System Last Rebooted' at '10 hours, 22 minutes, 37 seconds ago' and 'Load Averages' for 1 Minute (0.01), 5 Minutes (0.03), and 15 Minutes (0.00).
- Telephony Statistics:** Features a chart with a legend for 'Trunks Reged' (yellow), 'Trunks Offline' (red), and 'Active Calls' (blue). The chart shows a high volume of red bars, indicating many trunks are offline.
- Interpreter Statistics:** Includes a 'Sessions Status' table with 'Pending' (0) and 'Peak' (1) counts. Below it, statistics show 'Opened: 1', 'Error: 0', 'Refused: 0', and 'Max Duration: 4s'. An 'Average Counters' section shows 'Duration: 4.00', 'Response: 1.00', and 'CAPS: 0.00'.

The footer contains 'Version 1.0.117', '7 Nov 21:11:28', the 'voximal' logo with the tagline 'The voice interaction', a 'Support' link, and window/viewport size information: 'Window size: 1272 x 712', 'Viewport size: 1280 x 720'.

Select Setting → Voximal Setting → Test



## Get your PIN from the Asterisk console

Execute :

```
raspbx*CLI> voximal show license
Version      : V14.0
Build
CVS Revision : $Revision: 1.853 $
Gcc          : V4.9
Arch         : 32 bits
Target       : i686
Asterisk     : V13.11.2
Options sum  :
Date         : Nov  3 2016 21:40:06
Code         : b6de76bcb827eb415eb3b6f75b1001
UID          : cb773b52-a362-11e6-af57-b827eb415eb3
PIN          : 3152
Password     : cb773b52
Key          :
Max sessions : 1
Options
TextToSpeech : Yes
Speech       : Yes
State        : ok
```

Your PIN is : **3152** (in this example)

From:  
<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:  
[https://wiki.voximal.com/doku.php?id=installation\\_guide:test:start&rev=1478554849](https://wiki.voximal.com/doku.php?id=installation_guide:test:start&rev=1478554849)

Last update: **2016/11/07 21:40**

