

Call the test service

You can test your Voximal installation by calling the test numbers from any phone.

We setup 2 phone numbers :

- France : +33(0)9 72 53 88 23

You need to open the port 4569 from/to the internet. The calls will be transferred by this way to your Voximal server to the number/extension :

- **8965** ('VXML' from your phone dialpad).

By default, the Voximal installation configures the 'helloworld' service/account that executes this VoiceXML document :

- [helloworld.vxml](#)

When you call the voice portal, the service will request your PIN number.

Get your PIN from the Web Interface

With the Voxibot suite, the PIN number is prompted the main panel :

Test : Call +33(0)972 538 823 and enter your PIN XXXX

The screenshot displays the Voximal web interface. The top navigation bar includes 'Voximal', 'Reports', and 'Settings', along with a 'Logout: admin' button. The main content area is divided into several sections:

- System Overview:** Welcomes the user to ip-172-31-40-237. It prompts the user to call +33(0)972 538 823 and enter their PIN 2643. A summary table shows the status of various components:


| Component | Status |
|-------------|--------|
| Telephony | ✓ |
| Database | ✓ |
| Web Server | ✓ |
| Interpreter | ✓ |

 A green box indicates 'System Alerts: No critical issues found'. A blue box shows 'There are 2 bad destinations'.
- Uptime:** Shows the system was last rebooted 10 hours, 22 minutes, and 37 seconds ago. It also displays load averages for 1, 5, and 15 minutes.
- Telephony Statistics:** A chart showing the status of trunks (Reged, Offline, Active Calls) over time.
- Interpreter Statistics:** Shows sessions status with a bar chart for Pending and Peak sessions. It also displays average counters for Duration (4.00), Response (1.00), and CAPS (0.00).

The footer of the interface includes the version (1.0.117), date (7 Nov 21:11:28), the Voximal logo with the tagline 'The voice interaction', and a 'Support' link. A small box in the bottom right corner shows window and viewport sizes.

With standard FreePBX distribution :

- Select Setting → Voximal Setting → Test



Get your PIN from the Asterisk console

Execute :

```
raspbx*CLI> voximal show license
Version      : V14.0
Build
CVS Revision : $Revision: 1.853 $
Gcc          : V4.9
Arch         : 32 bits
Target       : i686
Asterisk     : V13.11.2
Options sum  :
Date         : Nov  3 2016 21:40:06
Code         : b6de76bcb827eb415eb3b6f75b1001
UID          : cb773b52-a362-11e6-af57-b827eb415eb3
PIN          : 3152
Password     : cb773b52
Key          :
Max sessions : 1
Options
TextToSpeech : Yes
Speech       : Yes
State        : ok
```

Your PIN is : **3152** (in this example)

From:
<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:
https://wiki.voximal.com/doku.php?id=installation_guide:test:start&rev=1483455031

Last update: **2017/01/03 14:50**

