

Call the test service

You can test your Voximal installation by calling the test numbers from any phone.

We setup 2 phone numbers :

- France : +33(0)9 72 53 88 23
- Unites States : +1-202-600-4534

You need to open the port 4569 from/to the internet. The calls will be transfered by this way to your Voximal server to the number/extension :

- **8965** ('VXML' from your phone dialpad).


By default, the Voximal installation configures the 'helloworld' service/account that executes this VoiceXML document :

- [helloworld.vxml](#)

When you call the voice portal, the service will request your PIN number.

Get your password from the Web Interface

Select Setting → Voximal Setting → Test



The screenshot shows the Voximal web interface. The top navigation bar includes links for Voximal, Connectivity, Reports, Settings, and an Apply Config button. The main content area is titled 'Voximal Settings' and has tabs for General, TextToSpeech, License, and Call Test. The 'Call Test' tab is active, displaying instructions: 'An easy way to make tests. To call your Voxibot : Call the +33(0)972538823 and enter the PIN number.' Below this, there are input fields for 'PIN' (with a question mark) and 'Port number' (with the value 4569). The footer contains version information (1.0.121, 18 Oct 10:10:11), the Voximal logo with the tagline 'The voice interaction', and a Support link.

Get your password from the Asterisk console

Execute :

```
raspbx*CLI> voximal show license
Version      : V14.0
Build
  CVS Revision : $Revision: 1.853 $
  Gcc          : V4.9
  Arch         : 32 bits
  Target       : i686
  Asterisk     : V13.11.2
  Options sum  :
  Date        : Nov  3 2016 21:40:06
Code         : b6de76bcb827eb415eb3b6f75b1001
UID          : cb773b52-a362-11e6-af57-b827eb415eb3
PIN          : 3152
Password     : cb773b52
Key          :
Max sessions : 1
Options
  TextToSpeech : Yes
  Speech       : Yes
State         : ok
```

Your password is : **cb773b52**

From:

<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:

https://wiki.voximal.com/doku.php?id=installation_guide:test:start&rev=1478505638

Last update: **2016/11/07 08:00**

