

Call the test service

You can test your Voximal installation by calling the test numbers from any phone.

We setup 2 phone numbers :

- France : +33(0)9 72 53 88 23

You need to open the port 4569 from/to the internet. The calls will be transfered by this way to your Voximal server to the number/extension :

- **8965** ('VXML' from your phone dialpad).

By default, the Voximal installation configures the 'helloworld' service/account that executes this VoiceXML document :


- [helloworld.vxml](#)

When you call the voice portal, the service will request your PIN number.

Get your PIN from the Web Interface

With the Voxibot suite, the PIN number is prompted the main panel :

Test : Call +33(0)972 538 823 and enter your PIN XXXX



With standard FreePBX distribution :

- Select Setting → Voximal Setting → Test

VoximalConnectivity ▾Reports ▾Settings ▾Apply ConfigLogout: adminLanguage ▾

Voximal Settings

GeneralTextToSpeechLicenseCall Test

An easy way to make tests.
To call your Voxibot :
Call the +33(0)972538823 and enter the PIN number.

PIN 	?
Port number 	4569

Version 1.0.121
18 Oct 10:10:11


The voice interaction

Support

Get your PIN from the Asterisk console

Execute :

```
raspbx*CLI> voximal show license
Version      : V14.0
Build
CVS Revision : $Revision: 1.853 $
Gcc          : V4.9
Arch         : 32 bits
Target       : i686
Asterisk     : V13.11.2
Options sum  :
Date        : Nov  3 2016 21:40:06
Code        : b6de76bcb827eb415eb3b6f75b1001
UID         : cb773b52-a362-11e6-af57-b827eb415eb3
PIN         : 3152
Password    : cb773b52
Key         :
Max sessions : 1
Options
TextToSpeech : Yes
Speech       : Yes
State        : ok
```

Your PIN is : **3152** (in this example)

From:

<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:

https://wiki.voximal.com/doku.php?id=installation_guide:test:start&rev=1484817220

Last update: **2017/01/19 09:13**

