

Verbio TTS

About

Verbio Technologies

Loreto 44
08029 Barcelona
Spain

Website: <http://www.verbio.com>

Definition

Verbio is a company based in Barcelona (Spain), specializing in speech technologies, aimed basically at the Spanish, Portuguese and Latin American markets.

Languages

English (US) · French · Portuguese · Portuguese (Brazil) · Spanish(Argentina) · Spanish (Chile) · Spanish (Venezuela) · Spanish (Colombia) · Spanish (Cuba) · Spanish (Santo Domingo) · Spanish (Puerto Rico) · Spanish (Paraguay) · Spanish (Uruguay) · Spanish(Mexico) · Spanish (North America) · Spanish (Catalan) · Spanish (Valencia) · Spanish (Galician) · Spanish (Euskera)

Installation

If your distribution does not use 'rpm' nor 'deb' please us to get specific installation packages or support.

Download the TTS binaries packages after contacting the Verbio sales.

```
# dpkg -i verbio-engines-x.yy.deb
# dpkg -i --force-overwrite verbio-clients-x.yy.deb
# dpkg -i --force-overwrite verbio-tts-*-x.yy.deb
# dpkg -i --force-overwrite verbio-asr-*-x.yy.deb (for the ASR)
```

If you have a license in a USB token, you need to install the USB token driver ('sntl-sud_x.y.z-w_i386.deb').

You will find the sntl package at:

```
/usr/share/doc/verbio
```

Then you start with:

```
# cd /usr/share/doc/verbio
# dpkg -i sntl-sud_7.3.0-1_i386.deb
```

You need to reboot the server to enable the USB daemon ().

If you have a file licence, please copy it to:

```
/opt/verbio/lic/
```

Download and install our connector package for Verbio.

First unzip and untar it by using the command:

```
# tar xvzf verbio_Vx.x_date.tar.gz
```

Next, go to the directory of the Verbio and type the following command:

```
# cd verbio_Vx.x_date
# ./install.sh
```

Configuration

The TTS package install the HTTP scripts in:

```
/var/www/tts/verbio
```


In a default Debian installation, you can test the TTS installation at:

```
http://yourip/tts/verbio/tts.html
```

This web page will generate your TTS raw alaw or ulaw files.

Release Notes

Install the script on your Apache/PHP server. Configure the VoiceXML Browser (Text-to-Speech Option) and restart the VoiceXML interpreter to get the new configuration.



From:

<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:

https://wiki.voximal.com/doku.php?id=legacy:text-to-speech_guide:verbio_tts:start

Last update: **2017/07/28 23:34**

