

Voxygen TTS

About

Voxygen Expressive Speech

Set up in 2011 and headquartered in Brittany on the northwest coast of France, Voxygen quickly ranked among the market leaders in the field of Speech Synthesis

Contact :

Route du Radôme
Pôle Phoenix - Bâtiment B1
22560 Pleumeur-Bodou
France
Tel +33 2 96 14 12 81
contact@voxygen.fr

Website: <http://www.voxygen.fr/en/>

Definition

Set up in 2011 and headquartered in Brittany on the northwest coast of France, Voxygen quickly ranked among the market leaders in the field of Speech Synthesis

Languages

English (US) · French · Portuguese · Portuguese (Brazil) · Spanish(Argentina) · Spanish (Chile) · Spanish (Venezuela) · Spanish (Colombia) · Spanish (Cuba) · Spanish (Santo Domingo) · Spanish (Puerto Rico) · Spanish (Paraguay) · Spanish (Uruguay) · Spanish(Mexico) · Spanish (North America) · Spanish (Catalan) · Spanish (Valencia) · Spanish (Galician) · Spanish (Euskera)

Installation

If your distribution does not use 'rpm' nor 'deb' please us to get specific installation packages or support.

Download the TTS binaries packages after contacting the Voxygen sales.

```
# dpkg -i Voxygen-engines-x.yy.deb  
# dpkg -i --force-overwrite Voxygen-clients-x.yy.deb  
# dpkg -i --force-overwrite Voxygen-tts-*-x.yy.deb
```

```
# dpkg -i --force-overwrite Voxygen-asr-*-x.yy.deb (for the ASR)
```

If you have a license in a USB token, you need to install the USB token driver ('sntl-sud_x.y.z-w_i386.deb').

You will find the sntl package at:

```
/usr/share/doc/Voxygen
```

Then you start with:

```
# cd /usr/share/doc/Voxygen
# dpkg -i sntl-sud_7.3.0-1_i386.deb
```

You need to reboot the server to enable the USB daemon ().

If you have a file licence, please copy it to:

```
/opt/Voxygen/lic/
```

Download and install our connector package for Voxygen.

First unzip and untar it by using the command:

```
# tar xvzf Voxygen_Vx.x_date.tar.gz
```

Next, go to the directory of the Voxygen and type the following command:

```
# cd Voxygen_Vx.x_date
# ./install.sh
```

Configuration

The TTS package install the HTTP scripts in:

```
/var/www/tts/Voxygen
```

In a default Debian installation, you can test the TTS installation at:

```
http://yourip/tts/Voxygen/tts.html
```

This web page will generate your TTS raw alaw or ulaw files.

Release Notes

Install the script on your Apache/PHP server. Configure the VoiceXML Browser (Text-to-Speech Option) and restart the VoiceXML interpreter to get the new configuration.

From:

<https://wiki.voximal.com/> - **Voximal documentation**

Permanent link:

https://wiki.voximal.com/doku.php?id=legacy:text-to-speech_guide:voxygen_tts:start&rev=1429275371

Last update: **2017/07/28 22:29**

